
ScanSnap Manager for fi Series 1.0.0
README

Copyright PFU LIMITED 2013

This file contains information about things you should know before using this product as well as the latest information, which is not included in Online Help topics.
Be sure to read this file prior to use.

* Use in High Safety Applications

This Product is designed, developed and manufactured as contemplated for general use, including without limitation, general office use, personal use, household use, and ordinary industrial use, but is not designed, developed and manufactured as contemplated for use accompanying fatal risks or dangers that, unless extremely high safety is secured, could lead directly to death, personal injury, severe physical damage or other loss (hereinafter "High Safety Required Use"), including without limitation, nuclear power reactioncore control in nuclearatomic facility, airplane automaticaircraft flight control, air traffic control, operation control in mass transport controlsystem, medical instrument for life support system, missile launching control in weapon system.

You shall not use this Product without securing the sufficient safety required for the High Safety Required Use.

In addition, PFU (or other affiliated company) shall not be liable against the Customer and/or any third party for any claims or damages arising in connection with the High Safety Required Use of the Product.

[Table of Contents]

1. System Requirements
2. Installation
3. Uninstallation
4. Notes

1. System Requirements

1) CPU, Memory, Hard disk drive

- Intel(R) Pentium(R) 4 1.8 GHz or higher (Recommended: Intel(R) Core(TM) i5 2.5 GHz or higher, except mobile device processors)
- 1 GB or more (Recommended: 4 GB or more)
- 5,400 rpm or more (Recommended: 7,200 rpm or more)

For more information about how to connect to the computer and other requirements, refer to the manual that comes with your scanner.

2) Operating Systems

- Windows(R) XP Home Edition (SP3 or later)
- Windows(R) XP Professional (SP3 or later)
- Windows(R) XP Professional x64 Edition (SP2 or later)
- Windows Vista(R) Home Basic (32-bit/64-bit) (SP1 or later)
- Windows Vista(R) Home Premium (32-bit/64-bit) (SP1 or later)
- Windows Vista(R) Business (32-bit/64-bit) (SP1 or later)
- Windows Vista(R) Enterprise (32-bit/64-bit) (SP1 or later)
- Windows Vista(R) Ultimate (32-bit/64-bit) (SP1 or later)
- Windows Server(R) 2008 Standard (32-bit/64-bit)
- Windows Server(R) 2008 R2 Standard (64-bit)
- Windows(R) 7 Home Premium (32-bit/64-bit)
- Windows(R) 7 Professional (32-bit/64-bit)

- Windows(R) 7 Enterprise (32-bit/64-bit)
 - Windows(R) 7 Ultimate (32-bit/64-bit)
 - Windows(R) 8 (32-bit/64-bit)
 - Windows(R) 8 Pro (32-bit/64-bit)
 - Windows(R) 8 Enterprise (32-bit/64-bit)
 - Windows Server(R) 2012 Standard (64-bit)
-

2. Installation

- * Be sure to log on as a user with Administrator privileges to install the program.
 - * When the User Account Control dialog box appears during installation, click the [Continue] button.
 - * Be sure to select a local folder as the installation folder.
 - * Do not install the program directly under the root folder. If the program is installed directly under the root folder, it may not work properly. Install the program in a folder other than the root folder.
 - * Do not use the following characters for the installation folder name. If any of the characters below is used, the program may not work properly.
/ ; : , . * ? " < > |
 - * To use SharePoint(R) Server, you need to install Scan to Microsoft SharePoint first.
 - * You are considered to have agreed with the License Agreement of Scan to Microsoft SharePoint upon installing it.
 - * The license fee on Scan to Microsoft SharePoint shall be included in that on the fi series.
 - * A warning message may appear during the installation of ScanSnap Manager for fi Series if a resident program such as anti-virus software is running.
-

3. Uninstallation

- * Be sure to log on as a user with Administrator privileges to uninstall the program.
 - * When the User Account Control dialog box appears during uninstallation, perform one of the following:
 - If you are logged on as a user with "administrator" privileges, click the [Continue] button.
 - If you are logged on as a user without "administrator" privileges, select a user with "administrator" privileges first, enter the password, and then click the [OK] button.
 - * Uninstall Microsoft .NET Framework after uninstalling Scan to Microsoft SharePoint.
-

4. Notes

1) About the operating environment

- This software does not guarantee reliable operations if used with Terminal Service Client or Remote Desktop Connection Client.
- To use this software, set the display to High Color or higher mode. If 256 or less color mode is selected, the display may be incorrect.

2) About supported drivers

- To use this software, you need to install the PaperStream IP (TWAIN) (32-bit) scanner driver.
-

- Microsoft, Windows, Windows Vista, Windows Server and SharePoint are either registered trademarks or trademarks of Microsoft Corporation in the United States and/or other countries.
- Intel, Pentium, and Intel Core are registered trademarks or trademarks of Intel Corporation in the United States and other countries.
- ScanSnap, the ScanSnap logo, ScanSnap Manager, and PaperStream are registered trademarks or trademarks of PFU LIMITED in Japan.
- Other company names and product names are the registered trademarks or trademarks of the respective companies.